





Setting up IMAP Mail on an Apple iPhone

Adding Users to the mail_relay group

Users that are wanting to use IMAP or SMTP authenticated mail on their machines or capable devices will need to be a member of the mail_relay group.

1. Login to the Smart-Net Intranet as sysadmin.
2. Click on Server Management → Users and Groups → Manage Groups
3. Click on the people icon to the right of mail_relay like below.

mail_relay	Users who belong to this group are allowed to relay mail after they have authenticated.	
moodle_courses	Users who belong to this group are able to create new courses in Moodle.	

4. Click on “+ Add Multiple Users”. Tick the users that you want to be part of this group. Click “Add Users”.

Setting up a new IMAP Account


1. To complete the mail setup, you need to know your IMAP server address. Login to the Smart-Net Intranet and click on ‘Server Information’ on the left.

E-Mail:	
IMAP Server:	intranet.smartcom.co.nz (192.168.1.1)
POP3 Server:	intranet.smartcom.co.nz (192.168.1.1)
SMTP Server:	intranet.smartcom.co.nz (192.168.1.1)
E-Mail Domain:	@smartcom.co.nz



Setting up your iPhone to use IMAP

1. Touch 'Settings', 'Mail, Contacts, Calendars'. Under Accounts, touch 'Add Account'.
2. In 'Add Account', touch 'Other'. Under Mail, touch 'Add Mail Account'.
3. Fill in your Full name, email address, account password. Change the description to be your name + IMAP. Touch 'Next'.



Telecom NZ 11:19 52%

Looking up account

Name Jane Doe

Address janedoe@smartcom.co.nz

Password ●●●●●●●●

Description smartcom.co.nz

4. Enter in your 'Incoming Mail Server' hostname, username and password and your 'Outgoing Mail Server' hostname, username and password. Touch 'Next'.



Telecom NZ 11:53 48%

Cancel **New Account** Next

Description Jane Doe IMAP

Incoming Mail Server

Host Name intranet.smartcom.co.nz

User Name janedoe

Password ●●●●●●●●

Outgoing Mail Server

Host Name intranet.smartcom.co.nz

User Name janedoe

Password ●●●●●●●●



5. It will then verify your account then allow you to select which features you would like to sync. Touch 'Save'.



6. It will bring you back to the 'Accounts' screen. Touch your new account.

7. It will then bring you to this screen. Touch 'Account'.





8. Scroll down to the bottom of the screen and touch 'SMTP'. Under 'Primary Server' touch the intranet option.



9. Touch SSL = on, authentication = password and Server Port = 587. Touch 'Done' then 'Account'.





10. Still down the bottom, touch 'Advanced'. Scroll down the bottom and turn SSL on for 'Incoming Settings'. 'Server Port' should be 993.



11. To go out of the mail settings, touch 'Account' then 'Done'. Then touch 'Mail' and this will bring you back to your 'Mail, Contacts and Calendar' settings page.

12. Test that you can send a receive emails.